



CalATERS Global Technical Specifications

As of August 4th, 2014

Assistive Technology:

Screen Reader: JAWS Professional v. 11

Please note: During testing it was determined in order for the JAWS product to function and interact properly with a java based application, the Sun Java Access bridge must be installed on any desktop that is running JAWS. The following URL can be found on the SUN web site describing the Java access bridge and instructions and help on how to download and install the bridge are available on the following web page:

<http://www.oracle.com/technetwork/java/javase/documentation/index-142733.html>

Note: This site was available as of 07/24/2014. If this site is no longer available, you can go to WWW.ORACLE.COM and do a search of that site for Java Access Bridge to get information.

The HTML pages for launching the application within the customer environment will not be modified by IBM to support accessibility. These web sites and HTML pages are created and maintained by the State of California.

Operating Systems:

Display Setting on MS Operating Systems: 1024 x 768

Windows XP

Component	Minimum Requirements
Browser (Applet)	Internet Explorer 7.0 / 8.0 / 9.0 / 10
Java	Sun Java 2 Plug-In 1.6.0_10 up to 1.7.0_51 *Version 7.10 was not compatible
RAM	128MB
Disk Space (Applet)	Approximately 3MB free space
Execution	There is a client approximately 1.5 MB in size cached on the desktop – distribution is over the web and automatically installed

	for new releases
--	------------------

Windows Vista

Component	Minimum Requirements
Browser (Applet)	Internet Explorer 7.0 / 8.0
Java	Sun Java 2 Plug-In 1.6.0 to 1.6.0_12
RAM	128MB
Disk Space (Applet)	Approximately 3MB free space
Execution	There is a client approximately 1.5 MB in size cached on the desktop – distribution is over the web and automatically installed for new releases

Windows 7

Component	Minimum Requirements
Browser (Applet)	Internet Explorer 8.0 / 9.0 / 10 / 11
Java	Sun Java 2 Plug-In 1.6.0_10 up to 1.7.0_67 *Version 7.10 was not compatible
PDF Viewer	Adobe Reader 9.3
RAM	128MB
Disk Space (Applet)	Approximately 3MB free space
Execution	There is a client approximately 1.5 MB in size cached on the desktop – distribution is over the web and automatically installed for new releases

A Windows 7 or greater computer with Java 7.x has the Java Access Bridge installed by default. The Java Access Bridge can be enabled by doing the following:

1. Start → Control Panel → Ease of Access Center → “Use the computer without a display”
2. Click on “Enable Java Access Bridge”
3. Click “Apply”

Mac OS X 10.4 (Tiger) and Max OS X 10.5.8 (Leopard)

Component	Minimum Requirements
Browser (Applet)	Safari 5.0.3 Firefox 2.0 / 3.0 -3.6.13
Java	Mac Java 1.5.0_07-26
RAM	128MB
Disk Space (Applet)	Approximately 3MB free space
Execution	There is a client approximately 2.2 MB in size cached on the desktop – distribution is over the web and automatically installed for new releases